

## Set Up IMAP - Opera

---

If you would like to learn more about the differences between POP and IMAP, please see the help topic, "[POP vs. IMAP](#)."

For increased security, we recommend that you use our secure (SSL) servers, as detailed below. **Note:** If your internal system configurations require non-SSL ports, please see the [Email Server Settings](#) page for our full list of available servers and ports.

To set up Opera for IMAP, do the following:

1. Select **Tools / Mail and Chat Accounts**.
2. The first time you choose this option, you'll see a setup wizard that will guide you through the steps of creating your email account. Click the **Yes** button.
3. Select **E-mail**, and click the **Next** button.
4. Enter the following:
  - Real name—Enter your first and last name. This is the name that will appear in the **From** field of messages you send.
  - E-mail address—Enter your entire email address (e.g., myname@mydomain.com).
  - Organization—Enter your company's name, or leave it blank for a personal account.
5. Click the **Next** button.
6. Enter the following:
  - Login name—Enter your entire email address (e.g., myname@mydomain.com).
  - Password— Enter the password for your email account.
  - Select an e-mail account type—Click the **IMAP** radio button.
7. Click the **Next** button.
8. Enter the following:
  - Incoming server—Enter the secure server name:

**secure.emailsrvr.com**

- Outgoing server—Enter the secure server name:

**secure.emailsrvr.com**

9. Select the **Use secure connection (TLS)** check boxes.



**New Account Wizard**

Incoming server

secure.emailsrvr.com

Use secure connection (TLS)


Outgoing server

secure.emailsrvr.com

Use secure connection (TLS)

< Back   Finish   Cancel   Help

10. Click the **Finish** button.
11. Select **Tools / Mail and Chat Accounts**.
12. Click once on your account, as it appears in the **Accounts** list.
13. Click the **Edit** button.
14. Click the **Servers** tab.
15. In the **Incoming IMAP server** section, enter the secure **Port number: 993**
16. In the **Outgoing SMTP server** section, enter the secure **Port number: 465**



**Account Properties** [X]

General Servers Incoming Outgoing

Incoming IMAP server

Server: secure.emailsrvr.com

Port number: 993  Secure connection (TLS)

Authentication: Auto (AUTH PLAIN)

Username: myname@mydomain.com

Password: [Password not displayed]

Outgoing SMTP server

Server: secure.emailsrvr.com

Port number: 465  Secure connection (TLS)

Authentication: Auto

Username: myname@mydomain.com

Password: [Password not displayed]

OK Cancel Help

17. Click the **OK** button.

18. Click the **Close** button.